Package 'dda'

November 14, 2025

Type Package
Title Direction Dependence Analysis
Version 0.1.1
License MIT + file LICENSE
Maintainer Wolfgang Wiedermann <wiedermannw@missouri.edu></wiedermannw@missouri.edu>
Description A collection of tests to analyze the causal direction of dependence in linear models (Wiedermann, W., & von Eye, A., 2025, ISBN: 9781009381390). The package includes functions to per form Direction Dependence Analysis for variable distributions, residual distributions, and independence properties of predictors and residuals in competing causal models. In addition, the package contains functions to test the causal direction of dependence in conditional models (i.e., models with interaction terms) For more information see https://www.ddaproject.com .
Imports dHSIC, energy, foreach, graphics, methods, stats
Suggests boot, doParallel, devtools, interactions, iterators, lmtest, moments, spelling, testthat (>= 3.0.0), waldo
Encoding UTF-8
RoxygenNote 7.3.3
Config/testthat/edition 3
<pre>URL https://github.com/wwiedermann/dda</pre>
NeedsCompilation no
Author Wolfgang Wiedermann [aut, cre], Megan Hirni [aut]
Repository CRAN
Date/Publication 2025-11-14 21:00:02 UTC
BugReports https://github.com/wwiedermann/dda/issues
Contents
cdda.indep
1

2 cdda.indep

cdda.indep

Conditional Direction Dependence Analysis: Independence Properties

Description

cdda.indep evaluates asymmetries of predictor-error independence of competing conditional models ($y \sim x * m vs. x \sim y * m with m being a continuous or categorical moderator).$

print returns the output of standard linear model coefficients for competing target and alternative models.

plot returns graphs for results of cdda.indep.

summary returns test statistics from the cdda.indep class object.

Usage

```
cdda.indep(
  formula = NULL,
  pred = NULL,
  mod = NULL,
 modval = NULL,
  data = list(),
 hetero = FALSE,
  diff = FALSE,
  nlfun = NULL,
  hsic.method = "gamma",
  B = 200,
  boot.type = "perc",
  conf.level = 0.95,
  parallelize = FALSE,
  cores = 1,
## S3 method for class 'cdda.indep'
print(x, ...)
## S3 method for class 'cdda.indep'
plot(x = NULL, stat = NULL, ylim = NULL, ...)
## S3 method for class 'cdda.indep'
summary(
```

cdda.indep 3

```
object,
nlfun = FALSE,
hetero = FALSE,
hsic = TRUE,
hsic.diff = FALSE,
dcor = TRUE,
dcor.diff = FALSE,
mi.diff = FALSE,
...
)
```

Arguments

formula

Symbolic formula of the model to be tested or an 1m object.

pred

A character indicating the variable name of the predictor which serves as the outcome in the alternative model.

mod

A character indicating the variable name of the moderator.

modval

Characters or a numeric sequence specifying the moderator values used in post-hoc probing. Possible characters include c("mean", "median", "JN").modval = "mean" tests the interaction effect at the moderator values M – 1SD, M, and M + 1SD; modval = "median" uses Q1, Md, and Q3. The Johnson-Neyman approach is applied when modval = "JN" with conditional effects being evaluated at the boundary values of the significance regions. When a numeric sequence is specified,the pick-a-point approach is used for the selected numeric values.

data

A required data frame containing the variables in the model.

hetero

A logical value indicating whether separate homoscedasticity tests should be returned when using summary, default is FALSE.

diff

A logical value indicating whether differences in HSIC, dCor, and MI values should be computed. Bootstrap confidence intervals are computed using B bootstrap samples.

nlfun

Determines handling of non-linear correlation tests depending on the function used:

- For cdda.indep: Either a numeric value or a function of .Primitive type used for non-linear correlation tests. When numeric, the value is used in a power transformation.
- For summary: A logical value indicating whether non-linear correlation tests should be returned in the output. Default is FALSE.

hsic.method

A character indicating the inference method for the Hilbert-Schmidt Independence Criterion. Must be one of the four specifications c("gamma", "eigenvalue", "boot", "permutation").hsic.method = "gamma" is the default.

В

Number of permutations for separate dCor tests and number of resamples when hsic.method = c("boot", "permutation") or diff = TRUE.

boot.type

A character indicating the type of bootstrap confidence intervals. Must be one of the two specifications c("perc", "bca"). boot.type = "perc" is the default.

conf.level

Confidence level for bootstrap confidence intervals.

4 cdda.indep

parallelize	A logical value indicating whether bootstrapping is performed on multiple cores. Only used if diff = TRUE.
cores	A numeric value indicating the number of cores. Only used if parallelize = TRUE.
• • •	Additional arguments to be passed to the function.
x	An object of class cdda.indep when using print or plot.
stat	A character indicating the CDDA statistic to be plotted with the options c("hsic.diff", "dcor.diff", "mi.diff").
ylim	A numeric vector of length 2 indicating the y-axis limits if NULL, the function will set the limits automatically.
object	An object of class cdda.indep when using summary.
hsic	A logical value indicating whether deparate HSIC tests should be returned when using summary, default is TRUE.
hsic.diff	A logical value indicating whether HSIC difference statistics should be returned when using summary, default is FALSE.
dcor	A logical value indicating whether separate Distance Correlation (dCor) tests should be returned when using summary, default is TRUE.
dcor.diff	A logical value indicating whether dCor difference statistics should be returned when using summary, default is FALSE.
mi.diff	A logical value indicating whether Mutual Information (MI) difference statistics should be returned when using summary, default is FALSE.

Value

An object of class dda.indep containing the results of independence tests of Conditional Direction Dependence Analysis.

An object of class cdda. indep with competing model coefficients.

References

Wiedermann, W., & von Eye, A. (2025). *Direction Dependence Analysis: Foundations and Statistical Methods*. Cambridge, UK: Cambridge University Press.

See Also

dda.indep for an unconditional version.

Examples

```
set.seed(321)
n <- 700

## --- generate moderator
z <- sort(rnorm(n))
z1 <- z[z <= 0]</pre>
```

cdda.vardist 5

```
z2 < -z[z > 0]
## --- x -> y when z <= 0
x1 \leftarrow rchisq(length(z1), df = 4) - 4
e1 < - rchisq(length(z1), df = 3) - 3
y1 < -0.5 * x1 + e1
## --- y -> x when m z > 0
y2 <- rchisq(length(z2), df = 4) - 4
e2 \leftarrow rchisq(length(z2), df = 3) - 3
x2 <- 0.25 * y2 + e2
y \leftarrow c(y1, y2); x \leftarrow c(x1, x2)
d <- data.frame(x, y, z)</pre>
m \leftarrow lm(y \sim x * z, data = d)
result <- cdda.indep(m,</pre>
                       pred = "x",
                       mod = "z",
                       modval = c(-1, 1),
                       data = d,
                       hetero = TRUE,
                       diff = TRUE,
                       parallelize = TRUE,
                       cores = 2,
                       nlfun = 2,
                       B = 2
# Note: Only 2 bootstrap samples are created here to lower computation time
print(result)
plot(result, stat = "dcor.diff")
summary(result, hetero = FALSE)
```

cdda.vardist

Conditional Directional Dependence Analysis: Variable Distributions

Description

cdda.vardist evaluates variable distributions of competing conditional models (y \sim x * m vs.x \sim y * m with m being a continuous or categorical moderator).

6 cdda.vardist

print returns the output of standard linear model coefficients for competing target and alternative models.

plot returns graphs for results of cdda.vardist.

summary returns test statistics from the cdda.vardist class object.

Usage

```
cdda.vardist(
  formula.
  pred = NULL,
 mod = NULL,
 data = list(),
 modval = NULL,
 B = 200,
 boot.type = "perc",
  conf.level = 0.95
)
## S3 method for class 'cdda.vardist'
print(x, ...)
## S3 method for class 'cdda.vardist'
plot(x, stat = NULL, ylim = NULL, ...)
## S3 method for class 'cdda.vardist'
summary(object, skew = TRUE, coskew = FALSE, kurt = TRUE, cokurt = FALSE, ...)
```

Arguments

tormula	Symbolic formula of the model to be tested of a 1m object
pred	A character indicating the variable name of the predictor which serves as the
	outcome in the alternative model.

A character indicating the variable name of the moderator.

mod A character indicating the variable name of the moderator.

data A required data frame containing the variables in the model.

Characters or a numeric sequence specifying the moderator values used in posthoc probing. Possible characters include c("mean", "median", "JN"). modval = "mean" tests the interaction effect at the moderator values M - 1SD, M, and M + 1SD; modval = "median" uses Q1, Md, and Q3. The Johnson-Neyman approach is applied when modval = "JN" with conditional effects being evaluated at the boundary values of the significance regions. When a numeric sequence is spec-

ified, the pick-a-point approach is used for the selected numeric values.

B Number of bootstrap samples.

boot.type A character indicating the type of bootstrap confidence intervals. Must be one

of the two values c("perc", "bca"). boot.type = "bca" is the default.

conf.level Confidence level for bootstrap confidence intervals.

x An object of class cdda. vardist when using print or plot.

cdda.vardist 7

• • •	Additional arguments to be passed to the function.
stat	A character indicating the statistic to be plotted, default is "rhs", with options $c("coskew", "cokurt", "rhs", "rcc", "rtanh")$.
ylim	A numeric vector of length 2 indicating the y-axis limits. If NULL, the function will set the limits automatically.
object	An object of class cdda.vardist when using summary.
skew	A logical value indicating whether skewness differences and separate D'Agostino skewness tests should be returned when using summary, default is TRUE.
coskew	A logical value indicating whether co-skewness differences should be returned when using summary, default is FALSE.
kurt	A logical value indicating whether excess kurtosis differences and Anscombe-Glynn kurtosis tests should be returned when using summary, default is TRUE.
cokurt	A logical value indicating whether co-kurtosis differences should be returned when using summary, default is FALSE.

Value

An object of class cdda.vardist containing the results of conditional direction dependence tests of variable distributions.

References

Wiedermann, W., & von Eye, A. (2025). *Direction Dependence Analysis: Foundations and Statistical Methods*. Cambridge, UK: Cambridge University Press.

See Also

dda.vardist for an unconditional version.

Examples

```
set.seed(321)
n <- 700

## --- generate moderator

z <- sort(rnorm(n))
z1 <- z[z <= 0]
z2 <- z[z > 0]

## --- x -> y when z <= 0

x1 <- rchisq(length(z1), df = 4) - 4
e1 <- rchisq(length(z1), df = 3) - 3
y1 <- 0.5 * x1 + e1

## --- y -> x when m z > 0

y2 <- rchisq(length(z2), df = 4) - 4</pre>
```

8 dda.indep

dda.indep

Direction Dependence Analysis: Independence Properties

Description

dda.indep evaluates asymmetries of predictor-error independence of causally competing models $(y \sim x \text{ vs. } x \sim y)$.

print returns DDA test statistics associated with dda.indep objects.

Usage

```
dda.indep(
  formula,
  pred = NULL,
  data = list(),
  nlfun = NULL,
 hetero = FALSE,
  hsic.method = "gamma",
  diff = FALSE,
  B = 200,
  boot.type = "perc",
  conf.level = 0.95,
  parallelize = FALSE,
  cores = 1
)
## S3 method for class 'dda.indep'
print(x, ...)
```

dda.indep 9

Arguments

formula	Symbolic formula of the model to be tested or a 1m object.
pred	A character indicating the variable name of the predictor which serves as the outcome in the alternative model.
data	An optional data frame containing the variables in the model (by default variables are taken from the environment which dda.indep is called from).
nlfun	Either a numeric value or a function of .Primitive type used for non-linear correlation tests. When nlfun is numeric the value is used in a power transformation.
hetero	A logical value indicating whether separate homoscedasticity tests (i.e., standard and robust Breusch-Pagan tests) should be computed.
hsic.method	A character indicating the inference method for the Hilbert-Schmidt Independence Criterion (HSIC). Must be one of the four specifications $c("gamma", "eigenvalue", "bootstrap", "permutation")$. hsic.method = "gamma" is the default.
diff	A logical value indicating whether differences in HSIC, Distance Correlation (dCor), and MI values should be computed. Bootstrap confidence intervals are computed using B bootstrap samples.
В	Number of permutations for separate dCor tests and number of resamples if $hsic.method = c("bootstrap", "permutation")$ or diff = TRUE.
boot.type	A vector of character strings representing the type of bootstrap confidence intervals. Must be one of the two specifications c("perc", "bca").boot.type = "perc" is the default.
conf.level	Confidence level for bootstrap confidence intervals.
parallelize	A logical value indicating whether bootstrapping is performed on multiple cores. Only used if $diff = TRUE$.
cores	A numeric value indicating the number of cores. Only used if $parallelize = TRUE$.
x	An object of class dda.indep when using print.
• • •	Additional arguments to be passed to the function.

Value

An object of class dda. indep containing the results of independence tests of Direction Dependence Analysis.

References

Wiedermann, W., & von Eye, A. (2025). *Direction Dependence Analysis: Foundations and Statistical Methods*. Cambridge, UK: Cambridge University Press.

See Also

cdda.indep for a conditional version.

10 dda.resdist

Examples

dda.resdist

Direction Dependence Analysis: Residual Distributions

Description

dda.resdist evaluates patterns of asymmetry of error distributions of causally competing models $(y \sim x \text{ vs. } x \sim y)$.

print returns DDA test statistics associated with dda.resdist objects.

Usage

```
dda.resdist(
  formula,
  pred = NULL,
  data = list(),
  B = 200,
  boot.type = "perc",
  prob.trans = FALSE,
  conf.level = 0.95
)

## S3 method for class 'dda.resdist'
print(x, ...)
```

Arguments

formula	Symbolic formula of the target model to be tested or a 1m object.
pred	Variable name of the predictor which serves as the outcome in the alternative model.
data	An optional data frame containing the variables in the model (by default variables are taken from the environment which dda.resdist is called from).
В	Number of bootstrap samples.

dda.vardist

boot.type	A vector of character strings representing the type of bootstrap confidence intervals required. Must be one of the two values c("perc", "bca"); boot.type = "perc" is the default.
prob.trans	A logical value indicating whether a probability integral transformation should be performed prior computation of skewness and kurtosis difference tests.
conf.level	Confidence level for bootstrap confidence intervals.
x	An object of class dda.resdist when using print.
	Additional arguments to be passed to the method.

Value

An object of class ddaresdist containing the results of direction dependence tests of error distributions.

References

Wiedermann, W., & von Eye, A. (2025). Direction Dependence Analysis: Foundations and Statistical Methods. Cambridge, UK: Cambridge University Press.

Examples

dda.vardist

Direction Dependence Analysis: Variable Distributions

Description

dda. vardist evaluates patterns of asymmetry of variable distributions for causally competing models (y \sim x vs. x \sim y).

print returns DDA test statistics associated with dda.vardist objects.

12 dda.vardist

Usage

```
dda.vardist(
  formula,
  pred = NULL,
  data = list(),
  B = 200,
  boot.type = "perc",
  conf.level = 0.95
)

## S3 method for class 'dda.vardist'
print(x, ...)
```

Arguments

formula	Symbolic formula of the model to be tested or a lmobject.
pred	Variable name of the predictor which serves as the outcome in the alternative model.
data	An optional data frame containing the variables in the model (by default variables are taken from the environment which dda.vardist is called from).
В	Number of bootstrap samples.
boot.type	A character indicating the type of bootstrap confidence intervals. Must be one of the two specifications $c("perc", "bca")$. boot.type = "perc" is the default.
conf.level	Confidence level for bootstrap confidence intervals.
x	An object of class dda.vardist when using print.
	Additional arguments to be passed to the function.

Value

An object of class dda.vardist containing the results of direction dependence tests of variable distributions.

An object of class dda.vardist.

References

Wiedermann, W., & von Eye, A. (2025). *Direction Dependence Analysis: Foundations and Statistical Methods*. Cambridge, UK: Cambridge University Press.

See Also

cdda.vardist for a conditional version.

dda.vardist

Examples

```
set.seed(123)
n <- 500

x <- rchisq(n, df = 4) - 4
e <- rchisq(n, df = 3) - 3
y <- 0.5 * x + e
d <- data.frame(x, y)

result <- dda.vardist(y ~ x, pred = "x", data = d, B = 50)
print(result)</pre>
```

Index

```
cdda.indep, 2, 9
cdda.vardist, 5, 12

dda.indep, 4, 8
dda.resdist, 10
dda.vardist, 7, 11

plot.cdda.indep (cdda.indep), 2
plot.cdda.vardist (cdda.vardist), 5
print.cdda.indep (cdda.indep), 2
print.cdda.vardist (cdda.vardist), 5
print.dda.indep (dda.indep), 8
print.dda.resdist (dda.resdist), 10
print.dda.vardist (dda.vardist), 11

summary.cdda.indep (cdda.indep), 2
summary.cdda.vardist (cdda.vardist), 5
```